

Configurar o Gerenciador de Tarefas do Windows

Após as configurações mencionadas, é necessário incluir o aplicativo nas tarefas agendadas do Windows. É uma etapa definida exclusivamente pelo time de TI já que impacta diretamente na capacidade dos servidores e necessidades de negócio.

- [Rodar sem exibir a tela preta](#)
- [Rodar exibindo tela preta](#)
- [Configuração de Contingência](#)

Rodar sem exibir a tela preta

Create Task

General Triggers Actions Conditions Settings

Name: **RoboDfe**

Location: \

Author: VERTEXINC\Tiago.Correa

Description:

Security options

When running the task, use the following user account:
VERTEXINC\Tiago.Correa **Change User or Group...**

☐ Run only when user is logged on

☒ **Run whether user is logged on or not**

☐ Do not store password. The task will only have access to local computer resources.

☒ **Run with highest privileges**

☐ Hidden

Configure for: Windows Vista™, Windows Server™ 2008

OK Cancel

Rodar exibindo tela preta

The 'Create Task' dialog box is shown with the 'General' tab selected. The 'Name' field contains 'RoboDfe'. The 'Location' field is empty. The 'Author' field contains 'VERTEXINC\Tiago.Correa'. The 'Description' field is empty. Under 'Security options', the text 'When running the task, use the following user account:' is followed by a text box containing 'VERTEXINC\Tiago.Correa' and a 'Change User or Group...' button. Below this, the radio button 'Run only when user is logged on' is selected and highlighted with a red rectangle. Other options include 'Run whether user is logged on or not', 'Do not store password. The task will only have access to local computer resources.', and 'Run with highest privileges' (checked). At the bottom, there is a 'Hidden' checkbox and a 'Configure for:' dropdown menu set to 'Windows Vista™, Windows Server™ 2008'. 'OK' and 'Cancel' buttons are at the bottom right.

Create Task

General Triggers Actions Conditions Settings

Name: RoboDfe

Location: \

Author: VERTEXINC\Tiago.Correa

Description:

Security options

When running the task, use the following user account:

VERTEXINC\Tiago.Correa Change User or Group...

☒ Run only when user is logged on

☐ Run whether user is logged on or not

☐ Do not store password. The task will only have access to local computer resources.

☒ Run with highest privileges

☐ Hidden Configure for: Windows Vista™, Windows Server™ 2008

OK Cancel

The 'Create Task' dialog box is shown with the 'Triggers' tab selected. The text 'When you create a task, you can specify the conditions that will trigger the task.' is at the top. Below it is a table with three columns: 'Trigger', 'Details', and 'Status'. The table is currently empty. At the bottom left, the 'New...' button is highlighted with a red rectangle. Other buttons are 'Edit...', 'Delete', 'OK', and 'Cancel'.

Create Task

General Triggers Actions Conditions Settings

When you create a task, you can specify the conditions that will trigger the task.

Trigger	Details	Status
---------	---------	--------

New... Edit... Delete

OK Cancel

New Trigger

Begin the task: On a schedule

Settings

☒ One time

☐ Daily

☐ Weekly

☐ Monthly

Start: 20/12/2023 15:18:16

☐ Synchronize across time zones

Advanced settings

☐ Delay task for up to (random delay): 1 hour

☒ Repeat task every: 5 minutes

for a duration of: Indefinitely

☐ Stop all running tasks at end of repetition duration

☐ Stop task if it runs longer than: 3 days

☐ Expire: 20/12/2024 15:18:18

☐ Synchronize across time zones

☒ Enabled

OK

Cancel

Create Task

General Triggers Actions Conditions Settings

When you create a task, you must specify the action that will occur when your task starts.

Action	Details
--------	---------

New...

Edit...

Delete

OK

Cancel

New Action ✕

You must specify what action this task will perform.


Action: Start a program ▾

Settings

Program/script:

Add arguments (optional):

Start in (optional):



Configuração de Contingência

Trata-se de uma configuração de contingência para o caso de travamento do Robô. Embora essa situação seja rara, caso ocorra, o Robô DF-e será reiniciado automaticamente após 12 horas, garantindo a continuidade dos serviços e evitando interrupções.

